FKEY	Action	Description
F1	levelmanager level offbyelem	Turns off levels by selected element
F2	view previous	Undo for view settings (zoom, level display)
F3	choose previous	Reactivates the Prevous Selection set
F4	choose none	Sets the selection set to none, puts "Home" in focus
F5	VBA Run ToggleAccuDraw	Toggles AccuDraw
F6	VBA Run ToggleCivilAccuDraw	Toggles Civil AccuDraw
F7	vba run toggleviewconstructions	Toggles construction elements in the view
F8	vba run snappabletoggle	Selects elements on grid line levels and turns off the snap parameter
F9	terrainmodel anayze terrainelevation	Reports terrain elevation at datapoint - Only works if terrain present in file
F10	terrainmodel analyze betweenpoints	Reports slope between two points on a terrain model
F11	terrainmodel analyze point	Reports station and offset from alignment
F12	corridor templatelibrary open	Opens template library
ALT + F1	Window ChangeScreen View 1;window tile;fit all;xy=,,,1;xy=,,,2;xy=,,,3;xy=,,,4;xy=,,,5;xy=,,,6;xy=,,,7;xy=,,,8;xy=,,,;choose none	Moves View 1 to other screen
ALT + F2	Window ChangeScreen View 2;window tile;fit all;xy=,,,1;xy=,,,2;xy=,,,3;xy=,,,4;xy=,,,5;xy=,,,6;xy=,,,7;xy=,,,8;xy=,,;choose none	Moves View 2 to other screen
ALT + F3	Window ChangeScreen View 3;window tile;fit all;xy=,,,1;xy=,,,2;xy=,,,3;xy=,,4;xy=,,5;xy=,,6;xy=,,7;xy=,,8;xy=,,;choose none	Moves View 3 to other screen
ALT + F4	Window ChangeScreen View 4;window tile;fit all;xy=,,,1;xy=,,,2;xy=,,,3;xy=,,,4;xy=,,,5;xy=,,,6;xy=,,,7;xy=,,,8;xy=,,,;choose none	Moves View 4 to other screen
ALT + F5	Window ChangeScreen View 5;window tile;fit all;xy=,,,1;xy=,,,2;xy=,,,3;xy=,,,4;xy=,,,5;xy=,,,6;xy=,,,7;xy=,,,8;xy=,,,;choose none	Moves View 5 to other screen
ALT + F6	Window ChangeScreen View 6;window tile;fit all;xy=,,,1;xy=,,,2;xy=,,,3;xy=,,,4;xy=,,,5;xy=,,,6;xy=,,,7;xy=,,,8;xy=,,,;choose none	Moves View 6 to other screen
ALT + F7	Window ChangeScreen View 7;window tile;fit all;xy=,,,1;xy=,,,2;xy=,,,3;xy=,,,4;xy=,,,5;xy=,,,6;xy=,,,7;xy=,,,8;xy=,,,;choose none	Moves View 7 to other screen
ALT + F8	Window ChangeScreen View 8;window tile;fit all;xy=,,,1;xy=,,,2;xy=,,,3;xy=,,,4;xy=,,,5;xy=,,,6;xy=,,,7;xy=,,,8;xy=,,,;choose none	Moves View 8 to other screen
ALT + F9	vba run TwoView3DF9	Opens two views, sets view two to 3D
ALT + F10	vba run OneView	Opens one view
ALT + F11	vba run ThreeViewsPLXS3D	Opens three views; Plan, Cross Section, and 3D
ALT + F12	vba run ThreeViewsPLPROF3D	Opens three views; Plan, Profile, and 3D
CTRL + F1	dialog reference toggle	Opens Reference Manager
CTRL + F2	model dialog toggle	Opens Model Manager
CTRL + F3	raster dialog toggle	Opens Raster Manager
CTRL + F4	pointcloud dialog toggle	Opens Point Cloud Manager
CTRL + F5	leveldisplay dialog toggle	Opens Level Display
CTRL + F6	levelmanager dialog toggle	Opens Level Manager
CTRL + F7	dialog cmdbrowse toggle	Opens Key-In browser
CTRL + F8	dialog cellmaintenance toggle	Opens Cell dialog
CTRL + F9	dialog explorer toggle	Project Explorer
CTRL + F10	dialog properties toggle	Element Information
CTRL + F11	dialog plot	Print single sheet
CTRL + F12	mdl load bentley.printorganizer; printorganizer dialog	Print Organizer
SHIFT + F1	dialog morewindows	Opens window dialog
SHIFT + F2	dialog toolsettings	Opens Toolsettings Dialog
SHIFT + F3	mdl load batchprocess	Opens Batch Process
SHIFT + F4	mdl load cleanup	Opens File Cleanup
SHIFT + F5	mdl load Selectby	Select By attributes
SHIFT + F6	dialog namedviews toggle	Opens Saved Views dialog